



WP-120A DATA VIEWER

WP-DataViewer

Instructions for Use

Thank you very much for using the WP-DataViewer.

Read this Instructions for Use before using it.

After reading it, keep it in a safe place for future reference.

Revision history

Revision	Date	Description
1.0.0	September 2022	First edition

Information is given about products in this Instructions for Use only for the purpose of example and does not indicate any guarantees against infringements of third-party intellectual property rights and other rights related to them. KYOWA ELECTRONIC INSTRUMENTS CO., LTD. will bear no responsibility for infringements on third-party intellectual property rights or their occurrence because of the use of these products.

- Microsoft and Windows are either registered trademarks or trademarks of Microsoft Corporation in the United States and/or other countries.
- Intel and Intel Core are trademarks of Intel Corporation or its subsidiaries.
- Other company names, product names and logos in this document are the trademarks or registered trademarks of their respective owners.
- The contents of this document could be changed without warning in the future.

NOTICE:

This SOFTWARE is protected by applicable copyright acts and international treaties. Unauthorized reproduction or distribution of this SOFTWARE, or any portion of it, may constitute infringement of any rights under applicable copyright acts, civil codes and other relevant laws and regulations, and further may result in criminal penalties or damages claimed.

This SOFTWARE is offered only on the condition that YOU agree to all terms and condition of the following End User License Agreement.

End User License Agreement

This End User License Agreement is an agreement between YOU and KYOWA ELECTRONIC INSTRUMENTS CO., LTD. (hereinafter referred to as "KYOWA") on the software, including computer programs, online or electronic documents, and if provided, any related record media, printed materials, and any software KYOWA may provide as the updates, additions or customizations for specific individual customers (hereinafter collectively referred to as "SOFTWARE"). By installing the SOFTWARE, it is deemed that YOU have agreed to be bound by the terms of this Agreement. In case YOU will not agree to the terms of this Agreement, YOU may not be allowed to use the SOFTWARE.

1. GRANT OF LICENSE

KYOWA grants YOU the right to use the SOFTWARE for using or processing the data recorded by qualified products that KYOWA designates (hereinafter referred to as "PRODUCT").

2. RESTRICTIONS

- YOU may not delete the copyright notices or any other proprietary legends on the SOFTWARE;
- YOU may not copy or distribute the SOFTWARE to any third party without the permission of KYOWA;
- YOU may not modify, reverse engineer, decompile, or disassemble the SOFTWARE;
- YOU may not rent or lease the SOFTWARE to any third party; and
- Only in case YOU transfer the SOFTWARE together with PRODUCT to the transferee perpetually, YOU may transfer YOUR rights under this Agreement to the transferee of the SOFTWARE, provided that the transferee agrees to comply with the terms and conditions of this Agreement.

3. TERMINATION

Without prejudice to any rights or claims to YOU, KYOWA may revoke YOUR rights under this Agreement if YOU breach this Agreement. In such event, YOU must immediately cease using the SOFTWARE, and must completely delete them.

4. COPYRIGHT

Any and all titles and copyrights in and to the SOFTWARE are reserved to KYOWA or the third parties who granted license to KYOWA (hereinafter referred to as "SUPPLIER").

5. NO WARRANTY

YOU ACKNOWLEDGE AND AGREE THAT ALL INFORMATION SUPPLIED BY KYOWA UNDER THIS AGREEMENT, INCLUDING WITHOUT LIMITATION THE SOFTWARE, IS PROVIDED BY KYOWA "AS IS" AND WITHOUT WARRANTY OF ANY KIND. KYOWA HEREBY DISCLAIMS ALL WARRANTIES, EXPRESS OR IMPLIED, WITH RESPECT TO THE SOFTWARE AND ANY MODIFICATION THEREOF BY YOU, INCLUDING BUT NOT LIMITED TO ANY WARRANTIES OF DESIGN, MERCHANTABILITY, FITNESS FOR A PARTICULAR PURPOSE, NON-INFRINGEMENT, OR WARRANTIES ARISING FROM A COURSE OF DEALING, USAGE, OR TRADE PRACTICE. KYOWA DOES NOT WARRANT THAT THE FUNCTIONS CONTAINED IN THE SOFTWARE WILL MEET YOUR REQUIREMENTS, OR THAT OPERATION OF THE SOFTWARE WILL BE UNINTERRUPTED OR ERROR-FREE, OR THAT DEFECTS IN THE SOFTWARE WILL BE CORRECTED, OR THAT YOU WILL HAVE OUR SUPPORT FOR YOUR USE OF THE SOFTWARE. KYOWA SHALL HAVE NO RESPONSIBILITY OR LIABILITY FOR ERRORS OR PRODUCT MALFUNCTION RESULTING FROM YOUR USE,

MODIFICATION, COPYING, OR DISTRIBUTION OF THE SOFTWARE. YOU assume complete responsibility for decisions made or actions taken based on information obtained using the Software. Any statements concerning the utility of the Software are not to be construed as expressed or implied warranties.

6. NO LIABILITY FOR CONSEQUENTIAL DAMAGES

TO THE MAXIMUM EXTENT PERMITTED BY APPLICABLE LAW, IN NO EVENT SHALL KYOWA AND THE SUPPLIER BE LIABLE FOR ANY SPECIAL INCIDENTAL, INDIRECT, OR CONSEQUENTIAL DAMAGES WHATSOEVER (INCLUDING, WITHOUT LIMITATION, DAMAGES FOR LOSS OF BUSINESS PROFITS, BUSINESS INTERRUPTION, DAMAGES FROM LOSS OF OR NON-OBTAINING OF BUSINESS INFORMATION OR DATA, OR ANY OTHER PECUNIARY LOSS) ARISING OUT OF THE USE OF OR INABILITY TO USE THE SOFTWARE, EVEN IF KYOWA HAS BEEN ADVISED OF THE POSSIBILITY OF SUCH DAMAGES. IN CASE ANY LAWS OR REGULATIONS IN SOME JURISDICTIONS DO NOT ALLOW THE EXCLUSION OR LIMITATION OF LIABILITY FOR CONSEQUENTIAL OR INCIDENTAL DAMAGES, THE LIMITATION WILL NOT APPLY TO YOU.

7. MISCELLANEOUS

This Agreement shall be construed in accordance with the laws of Japan.

All disputes arising in connection with this Agreement shall be submitted to the exclusive jurisdiction of the Tokyo District Court of Japan.

Should you have any questions concerning this Agreement, or if you desire to contact KYOWA for any reason, please write to the address or visit our website set forth below:

KYOWA ELECTRONIC INSTRUMENTS CO., LTD.

Chofugaoka 3-5-1, Chofu-shi, Tokyo 182-8520 Japan

<https://www.kyowa-ei.com/>

Instructions for Use overview

This Instructions for Use explains operation procedures for WP-DataViewer, which is a Windows PC data viewer program designed for use with WP-120A models.

Read the Instructions for Use for the WP-120A thoroughly before operating this program.

Conventions used in this Instructions for Use

Items and messages shown in the program are indicated with quotation marks, for example "MENU" and "Are you sure?"

Control buttons and selection items in the program are indicated with brackets, for example, [REC].

Index

1 – Overview	1
1.1. Introduction	1
1.2. Features	1
2 – Program installation	3
2.1. Recommended computer set up for WP-DataViewer	3
2.2. Installing WP-DataViewer	4
3 – Program operation	6
3.1. Launching and closing the program	6
3.2. Viewing data	7
3.2.1. Viewing (loading) data in a folder	7
3.2.2. Viewing lists	8
3.2.3. Viewing graphs	11
3.2.4. Changing graph display	15
3.3. Saving list data	16
3.4. Printing graphs	16
3.5. Copying graphs to the clipboard	16

1 – Overview

1.1. Introduction

WP-DataViewer is an offline data viewing program for WP-120A instrumentation amplifiers. Data can be shown in lists by folder, waveforms can be displayed and printed, and values totaled, for example.

1.2. Features

- Data recorded by a WP-120A can be shown in the following formats.
 - ⇒ Data recorded in a single folder can be shown in a list (with header information for file names, judgment results, hold values and other types of data)
 - ⇒ Hold value data in a single folder can be shown plotted (load or displacement)
 - ⇒ Hold value data in a single folder can be shown as a histogram (load or displacement)
 - ⇒ Hold value data in a single folder can be shown as statistical values (load or displacement)
 - ⇒ Any data in a single folder can be shown as a time series waveform (load or displacement)
 - ⇒ Any data in a single folder can be shown as a displacement–load waveform
- Listed header data can be output in CSV format
- Graphs can be printed and copied to the clipboard


Notes:

2 – Program installation

2.1. Recommended computer set up for WP-DataViewer


CPU:	2nd generation Intel® Core™ i5, 3.0 GHz or faster
OS:	Windows 10, Windows 7, Windows Vista, Windows XP
Memory:	4 GB or more
Hard drive open space:	10 GB or more
Screen resolution:	1024×768 pixels or more
.Net Framework	4 Client Profile

2.2. Installing WP-DataViewer




1. Double-click the WP-DataViewer installer (Setup.msi) to launch it.

Click [Next > (N)] to open the next screen.




2. Select the installation folder. Click [Browse... (R)] to change the folder.

Click [Next > (N)] to open the next screen.



3. A message to confirm the start of installation will appear. Click [Next > (N)] to start program installation.



4. When program installation completes, the next message will appear. Click


[Close (C)] to close the dialog.

Notes:


3 – Program operation

3.1. Launching and closing the program

In the Start menu at the bottom left of the screen, click [KYOWA] > [WP-DataViewer] to launch the WP-DataViewer program.



Toolbar explanation




Click  at the top right of the main window to close the program.


3.2. Viewing data

3.2.1. Viewing (loading) data in a folder

Click  in the toolbar to open the folder selection dialog.



Select the desired path and click [OK] to list the header data of the data files in the folder, and show the waveform that has been designated.






ATTENTION

⇒ Maximum quantity of data in a folder that can be processed is 262144. If the amount of data exceeds this, no data will be able to be listed.

⇒ The amount of time required to show the list is directly proportional to the amount of data in the folder. Moreover, the recording medium also affects the access speed.

3.2.2. Viewing lists

A list of header data for data files in the selected folder is shown on the left side of the window.



The meanings of the header data items are as follows.

- 1) File Data file name (extension not shown)
⇒ Only checked data will be reflected in the hold and hold histogram graphs.
- 2) Judgment Result Judgment result
OK/NG/H/L/HH/LL/NON or blank (none)
⇒ If displacement judgment is on for a WP-120, this will show load judgment followed by displacement judgment.
- 3) Hold (Load) Load at hold time
- 4) Hold (Disp.) Displacement at hold time
- 5) Hold Setting Hold setting
band/sample/peak/bottom/p-p/average/infect/maximum/minimum/multi
⇒ Multi (zone) holds will be shown as "multi-(each hold setting)".
- 6) WORK Work number
- 7) Judgment Condition Judgment condition
band/zone time/zone disp (zone displacement)
- 8) HI (HI (Load)) Judgment high limit value (when Judgment Condition is load/disp/zone time)
Judgment load high limit value (when Judgment Condition is zone/band/zone disp)
- 9) LO (HI (Load)) Judgment low limit value (when Judgment Condition is load/disp/zone time)
Judgment load low limit value (when Judgment Condition is zone/band/zone disp)
- 10) HI (HI (Disp.)) Judgment high high limit value (when Judgment Condition is load/zone time)
Judgment displacement high limit value (when Judgment Condition is zone/band/zone

- 11) LL (LO (Disp.) disp)
 Judgment low low limit value (when Judgment Condition is load/zone time)
 Judgment displacement low limit value (when Judgment Condition is zone/band/zone disp)
- 12) Number of Data Number of data points
 This is fixed at 2240. (This is the waveform data shown on the screen, not the raw data.)
- 13) Unit (Load) Load unit
- 14) Unit (Disp.) Displacement unit
 If the X axis is displacement, "-x" will be added to the end.
- 15) File Path File path name
- 16) Date Time Date and time

Multi-hold data overview

When multi-hold data is loaded, lists are created for each hold type.

A maximum of 6 lines are used per data point (Band 1, Zone 5).

File	J...	Hold (...)	Hold (...)	Hold Setting	Work
☒ WP 0301	OK	35.0	278.5	Multi-maximum	5M
☐ WP 0301	OK	65.7	437.5	Multi-infl...	5M
☐ WP 0301	OK	122.4	500.0	Multi-peak	5M
☒ WP 0302	OK	25.1	277.1	Multi-maximum	5M
☐ WP 0302	OK	55.8	437.5	Multi-infl...	5M
☐ WP 0302	OK	112.7	500.0	Multi-peak	5M
☒ WP 0303	OK	37.0	279.1	Multi-maximum	5M
☐ WP 0303	OK	67.6	437.5	Multi-infl...	5M
☐ WP 0303	OK	125.4	500.0	Multi-peak	5M

Individual hold type and judgment conditions are recorded for Judgment Result, Hold (Load), Hold (Disp.), Hold Setting, Judgment Condition, HI, LO, HH and LL items. For other items, the same information is recorded.

Moreover, hold type will be shown as "multi-(each hold setting)".

Checks in the list

Only data with checks in their check boxes (enabled) in the list will be reflected in the hold and hold histogram graphs. Check boxes are enabled by default. In the case of multi-hold data, however, only the first hold type will be on (second and third types will be off).


Click check boxes to turn them on/off.

File	J...	Hold (...)	Hold (...)	Hold S...	Work
☒ WP0001	OK	72.6	437.5	inflec...	2M
☒ WP0002	OK	78.9	437.5	inflec...	2M
☒ WP0003	OK	78.1	437.5	inflec...	2M
☒ WP0004	H	80.1	437.5	inflec...	2M
☒ WP0005	OK	69.6	437.5	inflec...	2M
☒ WP0006	OK	77.6	437.5	inflec...	2M
☒ WP0007	OK	79.5	437.5	inflec...	2M
☒ WP0008	OK	73.6	437.5	inflec...	2M
☒ WP0009	OK	79.1	437.5	inflec...	2M
☒ WP0010	H	80.6	437.5	inflec...	2M
☒ WP0011	OK	70.7	437.5	inflec...	2M
☒ WP0012	OK	76.8	437.5	inflec...	2M
☒ WP0013	OK	77.0	437.5	inflec...	2M
☒ WP0014	OK	70.9	437.5	inflec...	2M
☒ WP0015	OK	76.9	437.5	inflec...	2M

To turn multiple items on/off simultaneously, use the Shift or Ctrl key on the keyboard to select them, and then click one of their check boxes.

File	J...	Hold (...)	Hold (...)	Hold S...	Work
☒ WP0001	OK	72.6	437.5	inflec...	2M
☒ WP0002	OK	78.9	437.5	inflec...	2M
☒ WP0003	OK	78.1	437.5	inflec...	2M
☒ WP0004	H	80.1	437.5	inflec...	2M
☒ WP0005	OK	69.6	437.5	inflec...	2M
☒ WP0006	OK	77.6	437.5	inflec...	2M
☒ WP0007	OK	79.5	437.5	inflec...	2M
☒ WP0008	OK	73.6	437.5	inflec...	2M
☒ WP0009	OK	79.1	437.5	inflec...	2M
☒ WP0010	H	80.6	437.5	inflec...	2M
☒ WP0011	OK	70.7	437.5	inflec...	2M
☒ WP0012	OK	76.8	437.5	inflec...	2M
☒ WP0013	OK	77.0	437.5	inflec...	2M
☒ WP0014	OK	70.9	437.5	inflec...	2M
☒ WP0015	OK	76.9	437.5	inflec...	2M

In addition, clicking the [File] column name at the top of the list will open a "Select..." dialog.



If multi-hold data or multiple hold types have been recorded in a folder, this function can be used to check one hold type by itself.


3.2.3. Viewing graphs

Three graph display areas appear on the left side of the window. They can each be set to different display formats as desired.

The 7 display formats are Hold (Load), Hold (Disp), Hold Histogram (Load), Hold Histogram (Disp.), Time – Load, Time – Disp., and Disp -Load. They can be selected from the pulldown lists at the top left corner of each area.

Hold

Hold value trends and statistically calculated values (Data, OK/NG Count, Average, Maximum, Minimum, Variance, S.D, Fluct., Cp) are shown.



⇒ The horizontal axis is data number and the vertical axis is displacement or load.

⇒ Fluct. is a value calculated from $(S.D) \div (Average) \times 100$.

⇒ Cp shows the larger of the following two values:


$$\{(HI) - (Average)\} \div \{(S.D) \times 3\} \text{ or } \{(Average) - (LO)\} \div \{(S.D) \times 3\}$$

⇒ HI and HH are shown with red lines and LO and LL are shown with green lines.

⇒ Only data that has been checked in the list is shown in the hold graph.

Hold histogram

A hold value histogram and statistically calculated values (Data, OK/NG Count, Average, Maximum, Minimum, Variance, S.D, Fluct., Cp) are shown.



⇒ The horizontal axis is data number and the vertical axis is displacement or load.

⇒ Fluct. is a value calculated from $(S.D) \div (Average) \times 100$.

⇒ Cp shows the larger of the following two values:

$$\{(HI) - (Average)\} \div \{(S.D) \times 3\} \text{ or } \{(Average) - (LO)\} \div \{(S.D) \times 3\}$$

⇒ HI and HH are shown with red lines and LO and LL are shown with green lines.

⇒ Only data that has been checked in the list is shown in the hold histogram.

⇒ The values for each interval are determined automatically by the vertical display range and the number of divisions.



For example, if the display range is from 50 to 100, and the number of divisions is 10, the value of each interval will be as follows.

Interval 1:	50 to less than 55
Interval 2:	55 to less than 60
:	
:	
Interval 10:	95 to less than 100

Time series

Selected individual data points are shown.


In addition to clicking on the list, selection is also possible by clicking on the hold graph.



⇒ The horizontal axis is time and the vertical axis is displacement or load.

⇒ The high high limit is shown with a red line and the low low limit is shown with a green line.



Drag on the graph to show the cursor.



Load-displacement

Selected individual data points are shown.

In addition to clicking on the list, selection is also possible by clicking on the hold graph.



⇒ The horizontal axis is displacement and the vertical axis is load.

⇒ A cursor cannot be shown.

3.2.4. Changing graph display

Click a graph (or click the frames of hold and time series graphs) to open a dialog for changing the graph display range. Click [OK] to apply the changes. Click [Initialize] to restore all settings to their default values.

The image shows a 'Graph Property' dialog box with a close button (X) in the top right corner. It is divided into several sections:

- Graph1:** Type is 'Hold (Load)' (selected in a dropdown). There is an 'Auto Range' checkbox. X Axis is set from 0 to 300 with 10 divisions. Y Axis is set from 50 to 100 with 10 divisions. Both axes have a 'Grid' checkbox checked.
- Graph2:** Type is 'Disp. - Load' (selected in a dropdown). There is an 'Auto Range' checkbox. X Axis is set from 0 to 600 with 10 divisions. Y Axis is set from 0 to 130 with 13 divisions. Both axes have a 'Grid' checkbox checked.
- Graph3:** Type is 'Disp. - Load' (selected in a dropdown). There is an 'Auto Range' checkbox. X Axis is set from 0 to 200 with 10 divisions. Y Axis is set from 0 to 100 with 10 divisions. Both axes have a 'Grid' checkbox checked.
- Signal Type:** This section contains four rows: 'Time', 'Count', 'Load', and 'Disp.'. Each row has input fields for minimum, maximum, and divisions, and a 'Grid' checkbox. To the right of these rows are 'Auto Range' checkboxes.
- Sigma:** Located in the top right, it has three radio buttons: '3σ' (selected), '4σ', and 'OFF'.
- Buttons:** 'Initialize', 'OK', and 'CANCEL' buttons are located on the right side of the dialog.

The functions of the setting items are as follows.

Graph 1/2/3 setting items

- Type** Select the type of graph shown.
Hold (Load), Hold (Disp.), Hold Histogram (Load), Hold Histogram (Disp.), Time – Load, Time – Disp., Disp -Load
- X axis** Set the display range and the number of divisions shown with additional lines for the X axis.
For example, if the number of divisions is 10, 9 additional lines will divide the display area into 10 divisions.
- Y axis** Set the display range and the number of divisions shown with additional lines for the Y axis.
⇒ The number of divisions becomes the number of intervals for hold histogram display.
- Auto Range**
If checked, when the "Type" or a graph is changed, the graph axes will automatically be set to the axis ranges set in "Signal Type".

Signal Type setting items

- Time** Set the display range and the number of divisions for the time series axis.
If the Auto Range setting is checked, the display range will automatically be set to the recording time.
⇒ This is used for the Time (Load/Disp.) graph X axis.
- Count** Set the display range and the number of divisions for the data number axis.
If the Auto Range setting is checked, the display range will automatically be set to the number of data points.
⇒ This is used for the Hold (Load,Disp)/Hold Histogram (Load,Disp.) graph X axis.
- Load** Set the display range and the number of divisions for the load axis.
If the Auto Range setting is checked, the display range will be automatically set to the load value maximum and minimum.

(The maximum and minimum for auto range setting are the maximum and minimum hold load values for Hold (Load) and Hold Histogram (Load) graphs and the maximum and minimum time series load values for Time – Load and Disp. - Load graphs.)

⇒ This is used for the Hold (Load)/Hold Histogram (Load)/Time – Load/Disp. - Load graph Y axis.

Disp.

Set the display range and the number of divisions for the displacement axis.

If the Auto Range setting is checked, the display range will be automatically set to the displacement value maximum and minimum.

(The maximum and minimum for auto range setting are the maximum and minimum hold displacement values for Hold (Disp.) and Hold Histogram (Disp.) graphs and the maximum and minimum time series displacement values for Time – Disp. graphs.)

⇒ This is used for the Hold (Disp.), Hold Histogram (Disp.) and Time – Disp. Y axes, and for the Time – Disp. Graph X axis.

Sigma (σ) coefficient setting item

Sigma (σ) shows the standard deviation of statistical value calculations, and sets the range of the light green area shown in each graph.

OFF Light green area not shown.

3 σ The light green area shows a range of $\pm 3 \sigma$ from the average value.


4 σ The light green area shows a range of $\pm 4 \sigma$ from the average value.

3.3. Saving list data

Click  in the toolbar to open a file selection dialog, and save the header data shown in the list in CSV format.

3.4. Printing graphs


Click  in the toolbar to open the "Select a graph..." dialog.



This will only print the selected graph.

3.5. Copying graphs to the clipboard

Click  in the toolbar to open the "Select a graph..." dialog.



This will only copy the selected graph to the clipboard.

Note:

